MAKING VOTING ACCESSIBLE

PLAIN LANGUAGE & PLAIN INTERACTION

WHAT IF ANYONE COULD VOTE ON ANY DEVICE?

- Dana Chisnell, Usability Works
- Drew Davies, Oxide Designs
- Kathryn Summers, University of Baltimore

TABLET, SMARTPHONE, COMPUTER...

- Users can use their own device and their own, familiar, assistive technology
- Optimized for low literacy users
 - Plain language
 - Plain interaction

ABOUT THE BALLOT

• NIST medium complexity ballot, modified slightly

18 pages

 14 races, one constitutional amendment, two ballot measures

ABOUT THE TESTING

- Paper prototype
 - 18 participants
 - 4 days
 - 16 versions
- Digital Prototype
 - 15 participants
 - 4 days
 - 4 versions

Participants with

- Low literacy skills (4th to 8th grade reading level)
- Advanced age
- Mild cognitive impairments (i.e., short-term memory loss)

PLAIN LANGUAGE


- Ginny Redish and Dana Chisnell (2009) demonstrated the crucial role of plain language in ballot instructions for successful voting
- In our testing, we found that participants with lower literacy tended to act on every single word

MAKING IT PLAIN

Language tweaks that impacted voter success:

- Eliminating ambiguous words
- Reducing election jargon
- Reducing the amount of text on key screens
 - Introductory
 - Review
 - confirmation

BUTTON TEXT



- Several participants struggled with the "see additional candidates" button
- To ease use
 - Text was simplified
 - Jargon was eliminated

REVIEW SCREEN TEXT

Reenzes Gery	- 1100
V Contractions	Value
You could have voted for 4 c	andidates, out you only voted for 2
	touch hero.
l yax want to vote for more. Vator Commissioners	iouschi hiero.

🗸 Martalorithes	Velaw
/ Carde Boter	YHDAN
If you want to wate for mens to	and here a
Vater Commissioners	aut man.

After noting confusion from users, text on the review screen was changed:

"You could have voted for 4 candidates and you only voted for 2"

Became

"You voted for 2 people. You can vote for 2 more."

The change

- reduced election jargon
- focused on actions
- moved from familiar to new

CAST YOUR BALLOT

Are you sure you have finished voting?

Note: Once you press the Vote button, you will not be able to make any more changes.

If you want to make changes, touch the Return to ballot button.

If you are ready to cast your ballot, touch the Vote button.



Participants were confused and sometimes anxious about this page; they backed away from casting their vote.

Focusing the text on the message and the choice, rather than on the danger of making a mistake, allowed for easier processing and more confidence in voting.

NECESSARY HURDLES

Before you choose another name, touch the blue box on the name you don't want. That box will turn white. Then, touch the choice you do want.

This helps make sure you only change your vote when you mean to change it.

Close

Requiring users to deselect a choice before making a change is a known challenge

Our participants struggled with this

We simplified the text message, and bolded the key action (and made it easier to get out of the error message ©)

PLAIN LANGUAGE FINDINGS

- Minimal text, short sentences
- Specific, concrete, familiar words
- No jargon
- Large typesize

PLAIN INTERACTION

- Transition from paper ballots → electronic interfaces makes interaction design crucial
 - Previous research with low literacy participants on websites found that distractions, such as links, shifts in locus of action & sidebars, had detrimental effects on task success (Summer & Summers, 2005; Summers & Summers, 2006)
- Our ballot interface confirmed that distractions can similarly impede the voting process

PLAIN INTERACTION

- We started off simple, and had to get even more simple:
 - Focused on immediate action
 - Eliminated supplemental content
 - Removed extra icons
 - Removed the BACK button from all the screens in the Review process

INSTRUCTION SCREEN

How to vote	How to vote
To vote for the conditions of your choice, fourn that persons name. The box will turn bue.	To your for the condition of your shallos, touch that person's name. The box will tare blue.
To write in a candidate. To only for a person who is not on the ballot, thuch "Fouch here to write in a name." You will be more intercedures on the ballot, thuch "Fouch here to write in a name." You will be more intercedures on the to ongleta your write is. When you wont to change a vote or if you make a mistake, fruit fouch the ballot exclude you reske a mistake, fruit fouch the ballot exclude you reske a mistake, fruit fouch the ballot exclude you reske a mistake, fruit fouch the ballot exclude you reske a mistake, fruit fouch the ballot exclude you reske a mistake, fruit fouch the ballot exclude you reske a mistake, fruit fouch the ballot exclude you reske a mistake.	To write in a condition To write for a person who is not on the heliot, to ach "To uch here to write in a mems." You will get more instructions on how to complete sour write in. If you want to change your vote or if you make a mistake, first fouch the blue choice you no longer want. It have while again. Then bouch the shoke you do want. You do not have to vote in every race. Your ballot will call be counted even if you do not vote in every taxes.
You do not have to vote in every race. Your ballor will off the counted even if you do not yote in every race.	
You de not have to vote in every race. Your paint will still be counted even il you de not vote in every race.	

Users thought images on the instruction screen were interactive:

- Images were removed
- Text was reduced

BALLOT ITEM INSTRUCTIONS

Supreme Court Chief Judge

Choose Yes or No

To vote, touch a choice. A check mark (✓) will appear to show your choice.

To change your vote, touch the other choice.

If you want to keep Esther York as State Supreme Court Chief Justice, vote **Yes**.

If you do not want to keep Esther York as State Supreme Court Chief Justice, vote No.

Keep Esther York as Supreme Court Chief Judge?

Voting screens were streamlined, to focus all cognitive resources on the voting process itself

Instructions were removed to make screens more readable and clean

Even extra icons were eliminated

Supreme Court Chief Judge

-	Supreme Court Chief Judge Keep Esther York as Supreme Court Chief Judge?
à	Choose Yes or No
~	Yee

	Choose Yes or No		
~	Yes		
	No		

Keep Esther York as Supreme Court Chief Judge?

TEXT ENTRY

🕽 Write	in a nam	e for Reg	istrar of I	Deeds	
		vote for a pe			
To fini	sh, touch A	o cept . If you	i change you	ur mind, tou:	th Cancel.
ALBERTS	TERNER_				
A	в	c	D	E	F
G	Н	-1	J	к	L
м	N	0	Р	۵	R
s	т	U	v	w	x
Y	z	Sp	асе	+	
- E	rase				
∢ E	rase				

A non-QWERTY keyboard

- Supports text entry for those unused to typing
- We made the letters bigger → easier to identify
- We might change it even further, to start each line with a vowel (Sarah Swierenga's suggestion from K-12 practice)

PLAIN INTERACTION FINDINGS

		(T)
	Harvey Smith	Orange
	Randall Eagle	Orange
	Reid Davis	Orange
~	Barbere Shry	Yellow
~	Carole Barker	Yellow
1	Donald Rupp	Yellow
	Hugh Feister	Tan

• Find out what behaviors your participants want to use, and make them work if you can...

Our ballot lets users scroll by

- pressing a button
- dragging the scrollbar
- flicking a finger

PLAIN INTERACTION FINDINGS

Allow the users to touch anywhere on a name to select it

(i) Straight Party Vote

You can vote all at once for all the candidates from one political party. This is called a straight-party ticket.

If you want most candidates from one party, but some candidates from another party, you can vote straight party here. You can change your vote later for any of the races.

In some races, the candidates don't belong to a party. You will need to vote in these races later.

To vote straight party, touch the party name, and then touch Next.

To not vote straight party, just touch Skip.

1	Orange
	Yellow
	Tan
3	Sold

(1) Straight Party Vote

You can vote all at once for all the candidates from one political party. This is called a straight-party ticket.

If you want most candidates from one party, but some candidates from another party, you can vote straight party here. You can change your vote later for any of the races.

In some races, the candidates don't belong to a party. You will need to vote in these races later.

To vote straight party, touch the party name, and then touch Next.

To not vote straight party, just touch Skip.

Orange

Yell

Tan

Gold

SUPPORTING ERROR RECOVERY

Before you choose another name, touch the blue box on the name you don't want. That box will turn white. Then, touch the choice you do want.

This helps make sure you only change your vote when you mean to change it.

Close

We made the CLOSE button green, to match the action buttons in the main interface

We allowed users to press anywhere outside of the box to close it

PLAIN INTERACTION FINDINGS

- Support immediate action
- Eliminate distractions and disruptions
- Make natural user behaviors successful if possible
- Little things have big impact
- Iterative testing is a good way to be brilliant

UNFINISHED WORK

- A toggle to have instructions and messages read aloud
- A way to pause and resume voting
- Additional QA testing to perfect compatibility with assistive technologies